

O.P.I. Powder Perfection Protocol

STRUCTURE APPLICATION OVER A TIP

OPI Powder Perfection is an acrylic alternative that delivers a durable, chip resistant manicure for up to 3 weeks. Use OPI Powder Perfection to create structure over a tip for added length and strength.

WHAT YOU'LL NEED

Powder Perfection Products:
Clear Color Set Powder
Base Coat
Top Coat

Activator
N.A.S. 99 Cleansing Solution
Bond Aid pH Balancing Agent

Portion cups
Cosmetic brush
Nail wipes
180-grit file

100/180-grit buffer
220/280-grit buffer
Nail tips
ProSpa Nail & Cuticle Oil

THE STEPS




1

Prep those nails!
Follow OPI Salon Pro Service Prep steps prior to salon service application. Clean, prepped nails will ensure proper adhesion and wear of your OPI services.



2

Size the tips to each nail ensuring they cover the natural nail from one side to the other.



3

Apply a small amount of Powder Perfection Base Coat to the contact area of the nail tip.



4

Line the tip up to the natural nail, holding it at a 45-degree angle. If the tip has a stop point, guide the stop point up to the free edge of the nail and rock the tip up to meet the surface of the nail and hold for 3-5 seconds allowing the adhesive to set. Repeat on remaining nails.




5

Trim if desired. Use a 180-grit file to shape the nail tip to desired shape. Repeat on all nails.



6

Blend the tip to the natural nail with a 180-grit file, followed by a 100/180-grit buffer to further smooth and refine the tip. Optional: Use an e file with a medium carbide bit at medium speed in place of hand files if desired. Repeat on all nails.



7

Remove any dust from the nails with a cosmetic brush. Cleanse the natural nail with a nail wipe saturated with N.A.S. 99 Cleansing Solution.



8

Apply a coat of Bond Aid pH Balancing Agent to the natural nail.

PRO TIP

For remaining steps work on one hand at a time. This will ensure the first hand is set and ready to file after the second hand is finished.




9

Apply a thin line of Base Coat across the center of the nail where the tip and the nail meet leaving the sides bare. Immediately pour Clear Color Set Powder over the nail. Lightly brush away excess powder with a cosmetic brush. Repeat on the remaining fingers of the first hand.



10

Apply a thin coat of Base Coat to the center of the nail to reinforce the strength and begin creating an apex. Immediately pour Clear Color Set Powder over the nail. Lightly brush away the excess powder with a cosmetic brush. Repeat on remaining fingers of the first hand.



11

Apply a thin coat of Base Coat to a slightly larger section of the center of the nail to reinforce the strength and create the apex. Immediately pour Clear Color Set Powder over the nail. Lightly brush away the excess powder with a cosmetic brush. Repeat on remaining fingers of the first hand.



12

Apply a thin coat of Base Coat to the entire nail leaving a larger free margin around the perimeter of the nail. Immediately pour Clear Color Set Powder over the nail. Lightly brush away the excess powder with a cosmetic brush. Repeat on remaining fingers of the first hand.

PRO TIP

If applying GelColor over your Powder Perfection enhancement service DO NOT leave a larger free margin. Apply product up to the cuticle line leaving a very small free margin.



13

Apply a generous coat of Activator to the surface of the nail and along the extension edge of the nail. Allow product to set for 4 minutes before finish filing.



14

Shape and refine the surface of nails with a 180-grit file or an E-file with a medium carbide bit at a medium speed. Brush away dust with a cosmetic brush. Follow with OPI Powder Perfection Application Step-by-Steps to apply your shade of choice.

PRO TIP

If finishing with GelColor continue smoothing with a 100/180-grit buffer and cleanse nails with a nail wipe saturated with N.A.S. 99 before following OPI GelColor Application Step-by-Steps.

