

Clipping paths Basics



Once image is clipped, unwanted background is removed leaving a transparent background

What

A clipping path is an outline of your product created with the pen tool in Adobe Photoshop. It forms a single smooth line around the edge of the product, enabling you to remove the background.

Why

A clipping path enables your product to be used in retailer catalogues, online banners and advertising. Clipped image can easily be placed in solid background

Who

Major retailers including Coles and Woolworths will not accept images without a valid clipping path. Your graphic designer or photographer may be able to help create clipping paths.

Contact us

- E npccustomersupport@gs1au.org
- T 1300 227 263 (Option 3, 1)
- W gs1au.org/smart-media



Checklist

For an accurate clipping path, follow this checklist:

- The path has been created using the **Pen Tool** in Adobe Photoshop
- At 200% magnification, there is no background/ white space around the edge of the product
 - The clipping path has minimal anchor points and no jagged or rough edges
- There is only one path, saved and named as

 Path 1
- Image is saved in **.jpg** file format


Supported by







Check the image is 300dpi





The Steps

Here are the steps to follow, you will require Adobe Photoshop

- Open the image in Adobe Photoshop
- 2. Click on **Image** at the top menu bar
- 3. Scroll down to Image Size
- In the Image Size window, ensure the **Resolution** is at **300** and **Pixels/Inch** is selected
- 5. Save the images as .jpg

What

DPI is used to describe the number of 'dots per inch' in a digital print. The more dots, the higher the quality of the printed image.

Why

The 300dpi is to ensure you are sending high quality images to your retailers.

Who

Major retailers including Coles and Woolworths will not accept images under 300dpi. Your graphic designer or photographer may be able to help apply the correct resolution to your images.

Contact us

E npccustomersupport@gs1au.org

T 1300 227 263 (Option 3, 1)

W gs1au.org/smart-media

Supported by







Check for a Colour Profile Basics





The Steps

Here are the steps to follow, you will require Adobe Photoshop

- Open the image in Adobe Photoshop
- 2. Click on **Edit** at the top menu bar
- Scroll down to Assign Profile
- Your image must contain either one of the following profiles; Working RGB or Adobe RGB (1998)
- 5. Save the images as .jpg

What

Colour Profile is a standardised set of instructions that define how colours are represented and displayed within digital images.

Why

Colour Profile will ensure accurate and consistent colour representation of your images across devices and mediums.

Who

Major retailers including Coles and Woolworths will not accept images without a valid Colour Profile. Your graphic designer or photographer may be able to help apply a valid Colour Profile.

Contact us

- E npccustomersupport@gs1au.org
- T 1300 227 263 (Option 3, 1)
- W gs1au.org/smart-media

Supported by



